# Package 'influxdbclient'

July 14, 2021

0317 11, 2021
Title R Package for InfluxDB 2.x client
Version 0.1.0
<b>Description</b> R Package for InfluxDB 2.x client.
<pre>URL https://github.com/bonitoo-io/influxdb-client-r</pre>
BugReports https://github.com/bonitoo-io/influxdb-client-r/issues
<b>Depends</b> R (>= 3.3)
Encoding UTF-8
License MIT License + file LICENSE
LazyData true
<b>Imports</b> R6, httr, jsonlite, bit64, nanotime (>= 0.3.0), plyr
RoxygenNote 7.1.1
Suggests testthat, httptest
R topics documented:  InfluxDBClient
RetryOptions
Index 6
InfluxDBClient InfluxDBClient
Description
Client for querying from and writing to InfluxDB 2.x.
Format
An R6Class object

2 InfluxDBClient

#### **Public fields**

```
url Database URL
token Authentication token
org Organization name
dialect Flux dialect
retryOptions Retry options
```

#### Methods

#### **Public methods:**

```
• InfluxDBClient$new()
```

- InfluxDBClient\$health()
- InfluxDBClient\$query()
- InfluxDBClient\$ready()
- im taxbbettement cady (
- InfluxDBClient\$write()
- InfluxDBClient\$clone()

**Method** new(): Creates instance of InfluxDBClient.

```
Usage:
InfluxDBClient$new(url, token, org, retryOptions = NULL)
Arguments:
url InfluxDB instance URL
token Authentication token
org Organization name
org Retry options. See RetryOptions for details. Set to TRUE for default retry options. Default
```

is NULL which disables retries.

**Method** health(): Gets health info of the InfluxDB instance.

```
Usage:
```

InfluxDBClient\$health()

Returns: Named list with name, message, status, version, commit elements or error

**Method** query(): Queries data in the InfluxDB instance.

flatSingleResult Whether to return simple list when response contains only one result. Default is TRUE.

Returns: List of data frames. Data frame represents Flux table. It can be a named list of nested lists of data frames when query response contains multiple results (see https://docs. influxdata.com/influxdb/cloud/reference/flux/stdlib/built-in/outputs/yield/), or a simple list of data frames for single result response.

**Method** ready(): Gets readiness status of the InfluxDB instance.

```
Usage:
```

InfluxDBClient\$ready()

Returns: Named list with status, started and up elements or error

**Method** write(): Writes data to the InfluxDB instance.

```
Usage:
InfluxDBClient$write(
  х,
  bucket,
  batchSize = 5000,
  precision = c("ns", "us", "ms", "s"),
  measurementCol = "_measurement",
  tagCols = NULL,
  fieldCols = c(`_field` = "_value"),
  timeCol = "_time",
  object = NULL,
)
Arguments:
x Data as (list of) data.frame
bucket Target bucket name
batchSize Batch size. Positive number or FALSE to disable. Default is 5000.
precision Time precision
measurementCol Name of measurement column. Default is "_measurement".
tagCols Names of tag (index) columns
```

fieldCols Names of field columns. In case of unpivoted data previously retrieved from InfluxDB, use default value ie. named list c("\_field"="\_value"). For all other cases, just use simple vector of column names (see Examples).

timeCol Name of time column. The column values should be either of nanotime or POSIXct type. Default is "\_time".

object Output object name. For dry-run operation, specify the name of the object to receive the output. Default is NULL. For debugging purposes.

**Method** clone(): The objects of this class are cloneable with this method.

```
Usage:
InfluxDBClient$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

RetryOptions 4

#### **Examples**

```
## Not run:
# Instantiation
client <- InfluxDBClient$new(url = "http://localhost:8086",</pre>
                              token = "my-token",
                              org = "my-org")
# Query
data <- client$query('from(bucket: "my-bucket") |> range(start: -1h) |> drop(columns: ["_start", "_stop"])')
# Write
data <- data.frame(...)</pre>
client$write(data, bucket = "my-bucket", precision = "us",
             measurementCol = "name",
             tagCols = c("location", "id"),
             fieldCols = c("altitude", "temperature"),
             timeCol = "time")
# Ready status
ready <- client$ready()</pre>
# Healt info
ready <- client$health()</pre>
## End(Not run)
```

RetryOptions

RetryOptions

### **Description**

Retry options may be specified as optional argument to write.

#### **Format**

An R6Class object

#### **Public fields**

```
retryJitter Maximum number of random milliseconds included in delay. Default is 0. retryInterval First retry delay in seconds. Default is 5. maxDelay Maximum delay between retries in seconds. Default is 125. maxRetryTime Maximum time to spend retrying in seconds. Default is 180. maxAttempts Number of retry attempts. Default is 5. exponentialBase Base for exponential backoff strategy. Default is 2.
```

RetryOptions 5

## Methods

#### **Public methods:**

```
RetryOptions$new()RetryOptions$clone()
```

**Method** new(): Creates instance of RetryOptions.

```
Usage:
RetryOptions$new(
  retryJitter = 0,
  retryInterval = 5,
  maxDelay = 125,
  maxRetryTime = 180,
  maxAttempts = 5,
  exponentialBase = 2,
  ...
)
```

**Method** clone(): The objects of this class are cloneable with this method.

Usage:

RetryOptions\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

# **Index**

InfluxDBClient, 1

RetryOptions, 4