

Package ‘influxdbclient’

July 2, 2021

Title R Package for InfluxDB 2.x client

Version 0.1.0

Description R Package for InfluxDB 2.x client.

URL <https://github.com/bonitoo-io/influxdb-client-r>

BugReports <https://github.com/bonitoo-io/influxdb-client-r/issues>

Depends R (>= 3.3)

Encoding UTF-8

License MIT License + file LICENSE

LazyData true

Imports R6, httr, jsonlite, bit64, nanotime (>= 0.3.0), plyr

RoxygenNote 7.1.1

Suggests testthat, httpptest

R topics documented:

| | |
|--------------------------|---|
| InfluxDBClient | 1 |
| RetryOptions | 4 |

| | |
|--------------|----------|
| Index | 6 |
|--------------|----------|

| | |
|----------------|-----------------------|
| InfluxDBClient | <i>InfluxDBClient</i> |
|----------------|-----------------------|

Description

Client for querying from and writing to InfluxDB 2.x.

Format

An R6Class object

Public fields

url Database URL
token Authentication token
org Organization name
dialect Flux dialect
retryOptions Retry options

Methods**Public methods:**

- [InfluxDBClient\\$new\(\)](#)
- [InfluxDBClient\\$health\(\)](#)
- [InfluxDBClient\\$query\(\)](#)
- [InfluxDBClient\\$ready\(\)](#)
- [InfluxDBClient\\$write\(\)](#)
- [InfluxDBClient\\$as.lp\(\)](#)
- [InfluxDBClient\\$clone\(\)](#)

Method `new()`: Creates instance of InfluxDBClient.

Usage:

```
InfluxDBClient$new(url, token, org, retryOptions = NULL)
```

Arguments:

url InfluxDB instance URL
token Authentication token
org Organization name
org Retry options. See RetryOptions for details. Set to TRUE for default retry options. Default is NULL which disables retries.

Method `health()`: Gets health info of the InfluxDB instance.

Usage:

```
InfluxDBClient$health()
```

Returns: Named list with name, message, status, version, commit elements or error

Method `query()`: Queries data in the InfluxDB instance.

Usage:

```
InfluxDBClient$query(text, POSIXctCol = c(`_time` = "time"))
```

Arguments:

text Flux query
POSIXctCol Flux time to (new) POSIXct column mapping (named list). Default is `c("_time"="time")`.
Use NULL to skip it.

Returns: Data as (list of) `data.frame`

Method `ready()`: Gets readiness status of the InfluxDB instance.

Usage:

```
InfluxDBClient$ready()
```

Returns: Named list with status, started and up elements or error

Method `write()`: Writes data to the InfluxDB instance.

Usage:

```
InfluxDBClient$write(
  x,
  bucket,
  batchSize = 5000,
  precision = c("ns", "us", "ms", "s"),
  measurementCol = "_measurement",
  tagCols = NULL,
  fieldCols = c(`_field` = "_value"),
  timeCol = "_time",
  ...
)
```

Arguments:

`x` Data as (list of) `data.frame`

`bucket` Target bucket name

`batchSize` Batch size. Positive number or FALSE to disable. Default is 5000.

`precision` Time precision

`measurementCol` Name of measurement column. Default is "_measurement".

`tagCols` Names of tag (index) columns

`fieldCols` Names of field columns. In case of unpivoted data previously retrieved from InfluxDB, use default value ie. named list `c("_field" = "_value")`. For all other cases, just use simple vector of column names (see Examples).

`timeCol` Name of time column. The column values should be either of nanotime or POSIXct type. Default is "_time".

Method `as.lp()`: Coerces data to InfluxDB line protocol. *For debugging and introspection purposes. Parameters are the same as for write method.*

Usage:

```
InfluxDBClient$as.lp(
  x,
  precision = c("ns", "us", "ms", "s"),
  measurementCol = "_measurement",
  tagCols = NULL,
  fieldCols = c(`_field` = "_value"),
  timeCol = "_time"
)
```

Returns: line protocol text

Method `clone()`: The objects of this class are cloneable with this method.

Usage:

```
InfluxDBClient$clone(deep = FALSE)
```

Arguments:

`deep` Whether to make a deep clone.

Examples

```
## Not run:
# Instantiation
client <- InfluxDBClient$new(url = "http://localhost:8086",
                             token = "my-token",
                             org = "my-org")

# Query
data <- client$query('from(bucket: "my-bucket") |> range(start: -1h) |> drop(columns: ["_start", "_stop"])')

# Write
data <- data.frame(...)
client$write(data, bucket = "my-bucket", precision = "us",
             measurementCol = "name",
             tagCols = c("location", "id"),
             fieldCols = c("altitude", "temperature"),
             timeCol = "time")

# Ready status
ready <- client$ready()

# Health info
ready <- client$health()

## End(Not run)
```

RetryOptions

RetryOptions

Description

Retry options may be specified as optional argument to `write`.

Format

An R6Class object

Public fields

`retryJitter` Maximum number of random milliseconds included in delay. Default is 0.

`retryInterval` First retry delay in seconds. Default is 5.

`maxDelay` Maximum delay between retries in seconds. Default is 125.

`maxRetryTime` Maximum time to spend retrying in seconds. Default is 180.

`maxAttempts` Number of retry attempts. Default is 5.

`exponentialBase` Base for exponential backoff strategy. Default is 2.

Methods**Public methods:**

- [RetryOptions\\$new\(\)](#)
- [RetryOptions\\$clone\(\)](#)

Method `new()`: Creates instance of `RetryOptions`.

Usage:

```
RetryOptions$new(  
  retryJitter = 0,  
  retryInterval = 5,  
  maxDelay = 125,  
  maxRetryTime = 180,  
  maxAttempts = 5,  
  exponentialBase = 2,  
  ...  
)
```

Method `clone()`: The objects of this class are cloneable with this method.

Usage:

```
RetryOptions$clone(deep = FALSE)
```

Arguments:

`deep` Whether to make a deep clone.

Index

InfluxDBClient, [1](#)

RetryOptions, [4](#)